

Configuring Eudora 6 for Mac OS X to use your new e-mail account


Eudora is popular e-mail program available for Mac OS X. The following instructions provide a walk through on setting up Eudora to use your e-mail account.

What you need to know:

- Your e-mail address (Our example will use jsmith@mydomain.com.au)
- Your password
- Your e-mail server address (Our example will use mail.mydomain.com.au)

Note: You may elect to use your Internet Service Providers outgoing e-mail server to send your e-mail. In this case you will need to also know the ISP outgoing (SMTP) server name as well.

1. Start Eudora.
2. Go to the Eudora menu and then select Preferences.



3. Select Getting Started from the left hand list.

Enter your e-mail address as your User Name.


Enter your e-mail server address into the Mail Server field. Your incoming mail server is mail. followed by your domain name. For our example the domain is mydomain.com.au, so this means that our incoming mail server is mail.mydomain.com.au

Enter the name that you wish people to see when they receive e-mail from you into the Real Name field. This is most commonly your first name followed by your last name.

You have two options for your SMTP (outgoing) mail server. You may use the same address as your incoming mail server, or you may use your Internet Service Providers (ISP) mail server.

Some people find that their ISP may block mail being sent to other mail servers, so in this situation they need to use their ISP's mail server instead. The ISP mail server is generally mail. followed by the ISP's domain name. So for example if we take Bigpond who do require this configuration to be used, you enter mail.bigpond.com as your outgoing mail server.

Enter your e-mail address.



The image shows a screenshot of an email configuration dialog box. It is divided into two main sections: 'Checking Mail' and 'Sending Mail'.
In the 'Checking Mail' section, there are two text input fields: 'User Name:' containing 'jsmith@mydomain.com.au' and 'Mail Server:' containing 'mail.mydomain.com.au'.
In the 'Sending Mail' section, there are three text input fields: 'Real Name:' containing 'John Smith', 'SMTP Server:' containing 'mail.mydomain.com.au' with a note below it: '(You only need to fill this in if it's different from your Mail Server above.)', and 'Email Address:' containing 'jsmith@mydomain.com.au' with a note below it: '(You only need to fill this in if it's different from Username@MailServer.)'. The 'Email Address' field is highlighted with a blue border.

4. Click OK, and you are now ready to use your e-mail.

You may send an e-mail to your own e-mail address to test if it is working. Wait about 30 seconds and then click the Check Mail button to see your test e-mail arrives in your inbox.

Important Information

Your new mail server features security to prevent unauthorised access and spamming.

When using your new e-mail server as the outgoing mail server in Eudora (ie mail.mydomain.com.au), the e-mail address you enter into the account settings of Eudora must match your username.

For example if your username is jsmith@mydomain.com.au you must enter your e-mail address as jsmith@mydomain.com.au.

If your e-mail address does not match your username, the server will refuse to send your outgoing e-mail messages.

For example your username is jsmith@mydomain.com.au but you enter jsmith@somewhereelse.com.au as your e-mail address.

This does not apply if you are using your ISP's mail server as your outgoing e-mail server.